
ALGORITHM 1: Classical Reservoir Computer (CRC)

- 1: Pre-process the input data time-series $\mathbf{u}_{in}(t_i)$.
 - 2: Random and sparse input weight matrix $\mathbf{W}_{in}$ maps the input to high dimensional reservoir.
 $\triangleright \mathbf{W}_{in} \mathbf{u}_{in}(t_i)$
 - 3: Random reservoir weight matrix $\mathbf{W}$ with specified connectivity provides connections and the flow of information between different neurons in the reservoir.
 - 4: Run reservoir update to calculate reservoir activation states $\mathbf{r}(t_{i+1})$ from the input $\mathbf{u}_{in}(t_i)$.
 $\triangleright \tanh(\mathbf{W}_{in} \mathbf{u}_{in}(t_i) + \mathbf{W} \mathbf{r}(t_i))$
 - 5: Compute linear readout weight $\mathbf{W}_{out}$ by minimizing the MSE between predicted and true output, using linear ridge regression.
 - 6: Make predictions using the trained $\mathbf{W}_{out}$ matrix and the reservoir activation states $\mathbf{r}(t_{i+1})$. Use open-loop configuration for one-step-ahead predictions and the closed-loop configuration for the autonomous predictions from the input data.
-

ALGORITHM 2: Quantum Reservoir Computer (QRC)

- 1: Pre-process the input data time-series $\mathbf{u}_{in}(t_i)$ and encode it into the quantum circuit using rotational encoding.
 - 2: Use the specified quantum feature maps to map the input data to the high-dimensional Hilbert space. Here, U represents unitary evolution of the quantum state.
 $\triangleright U(\mathbf{u}_{in}(t_i))$
 - 3: Apply an additional unitary $V(\alpha)$ sampling from a uniform random distribution to provide randomization in the quantum circuit.
 - 4: Quantum reservoir state update $|\psi(t_{i+1})\rangle$ is achieved by running the quantum circuit with the encoded input data $\mathbf{u}_{in}(t_i)$, previous reservoir states $|\psi(t_i)\rangle$ and the additional random unitary.
 $\triangleright V(\alpha) \Phi(\mathbf{u}_{in}(t_i)) P(\mathbf{r}(t_i)) |\mathbf{0}\rangle$.
 - 5: Measure the quantum circuit in a Pauli-Z basis to convert quantum reservoir state $|\psi(t_{i+1})\rangle$ to classical reservoir state $\mathbf{r}(t_{i+1})$. Re-encode the measured $\mathbf{r}(t_{i+1})$ to P unitary for the next time-step.
 - 6: Repeat steps 5 and 6 similarly to a classical reservoir computer, to train the network and make predictions by repeating the quantum reservoir state updates.
-