

Example: HHO Poisson

```
1 using Test
2 using Gridap
3 using Gridap.Geometry, Gridap.FESpaces
4 using Gridap.MultiField, Gridap.CellData
5 using Gridap.ReferenceFES, Gridap.Arrays
6
7 u_exact(x) = x[1] + x[2]
8 f(x) = -Δ(u_exact)(x)
9
10 model = voronoi_mesh((0,1,0,1),(6,6))
11 Ω = Triangulation(ReferenceFE{2}, model)
12 Γ = Triangulation(ReferenceFE{1}, model)
13
14 order = 1
15
16 ptopo = PatchTopology(model)
17 Ωp = PatchTriangulation(model,ptopo)
18 Γp = PatchBoundaryTriangulation(model,ptopo)
19
20 qdegree = 2*(order+1)
21 dΩp = Measure(Ωp,qdegree)
22 dΓp = Measure(Γp,qdegree)
23
24 V = PolytopalFESpace(Ω, Float64, order)
25 M = PolytopalFESpace(
26   Γ, Float64, order; dirichlet_tags="boundary"
27 )
28 N = TrialFESpace(M,u_exact)
29
30 style = BlockMultiFieldStyle(2,(1,1))
31 X = MultiFieldFESpace([V, N];style=style)
32 Y = MultiFieldFESpace([V, M];style=style)
33
34 hT = CellField(sqrt.(get_cell_measure(Ωp)), Ωp)
35 R = reconstruction_operator(Ω,ptopo,X,order)
36 PΓ = projection_operator(M, Γp, dΓp)
37 PΩ = projection_operator(V, Ωp, dΩp)
38
39 function a((RuT,RuF),(RvT,RvF))
40   ∇Ru = ∇(RuT) + ∇(RuF)
41   ∇Rv = ∇(RvT) + ∇(RvF)
42   return ∫(∇Ru · ∇Rv)dΩp
43 end
44
45 l((vΩ,vΓ)) = ∫(f·vΩ)dΩp
46 s(u,v) = ∫((1/hT)*(u·v))dΓp
47
48 function S1((uT,uF))
49   return PΓ(uT) - uF
50 end
51 function S2((RuT,RuF))
52   PΓRuT, PΓRuF = PΓ(RuT), PΓ(RuF)
53   PΩRuT, PΩRuF = PΩ(RuT), PΩ(RuF)
54   return (PΓRuT - PΩRuT) + (PΓRuF - PΩRuF)
55 end
56
57 function weakform(ptopo,assem,X,Y)
58   Xp = FESpaces.PatchFESpace(X,ptopo)
59   u, v = get_trial_fe_basis(X), get_fe_basis(Y);
60
61   Ru, Rv = R(u), R(v)
62   S1u, S1v = S1(u), S1(v)
63   S2u, S2v = S2(Ru), S2(Rv)
64   z = DomainContribution()
65
66   data = collect_and_merge_cell_matrix_and_vector(
67     assem,
68     (X, X, s(S1u,S1v), l(v), zero(X)),
69     (X, Xp, s(S1u,S2v), z, zero(X)),
70     (Xp, X, s(S2u,S1v), z, zero(Xp)),
71     (Xp, Xp, a(Ru,Rv) + s(S2u,S2v), z, zero(Xp)),
72   )
73   return assemble_matrix_and_vector(assem,data)
74 end
75
76 assem = PatchAssembler(ptopo,X,Y)
77 op = StaticCondensationOperator(
78   X,assem,weakform(ptopo,assem,X,Y)
79 )
80
81 xh = solve(op)
82 uT, uF = xh
83
84 eh = R(xh) - u_exact
85 l2_err = sqrt(sum( ∫(eh * eh)dΩp))
86 h1_err = l2_err + sqrt(sum( ∫(∇(eh) · ∇(eh))dΩp))
```