

Example: Mixed-order HHO Optimal Control

```
1 using Gridap
2 using Gridap.Geometry, Gridap.FESpaces
3 using Gridap.CellData, Gridap.Fields
4 using Gridap.ReferenceFES, Gridap.Helpers
5 using Gridap.Arrays, Gridap.MultiField
6
7 uex(x) = sin(2π*x[1])*sin(2π*x[2])
8 pex(x) = -10*sin(2π*x[1])*sin(2π*x[2])*
9     x[1]*(x[1]-1)*x[2]*(x[2]-1)
10 za = -1; zb = 1; λ = 0.01
11 zex(x) = max( za, min(zb, -(1/λ) * pex(x)) )
12 f(x) = -Δ(uex)(x) - zex(x)
13 yd(x) = uex(x) + Δ(pex)(x)
14
15 model = mesh_voronoi((0,1,0,1), (8,8))
16 Ω = Triangulation(ReferenceFE{2}, model)
17 Γ = Triangulation(ReferenceFE{1}, model)
18
19 ptopo = PatchTopology(model)
20 Ωp = PatchTriangulation(model,ptopo)
21 Γp = PatchBoundaryTriangulation(model,ptopo)
22
23 order = 1
24 qdegree = 2*(order+1)
25 dOp = Measure(Ωp,qdegree)
26 dΓp = Measure(Γp,qdegree)
27 # State
28 Vs = PolytopalFESpace(Ω, Float64, order+1)
29 Ms = PolytopalFESpace(Γ, Float64, order;
30     dirichlet_tags="boundary")
31 Ls = PolytopalFESpace(Ω, Float64, order+1)
32 Ns = TrialFESpace(Ms, uex)
33 # Adjoint
34 Va = PolytopalFESpace(Ω, Float64, order+1)
35 Ma = PolytopalFESpace(Γ, Float64, order;
36     dirichlet_tags="boundary")
37 La = PolytopalFESpace(Ω, Float64, order+1)
38 Na = TrialFESpace(Ma, pex)
39
40 style = MultiField.BlockMultiFieldStyle(2,(1,1))
41 Xs = MultiFieldFESpace([Vs, Ns];style=style)
42 Ys = MultiFieldFESpace([Vs, Ms];style=style)
43 Xa = MultiFieldFESpace([Va, Na];style=style)
44 Ya = MultiFieldFESpace([Va, Ma];style=style)
45
46 Pfs = projection_operator(Ms, Γp, dΓp)
47 Pfa = projection_operator(Ma, Γp, dΓp)
48 Rs = reconstruction_operator(Ω, ptopo, Xs, order)
49 Ra = reconstruction_operator(Ω, ptopo, Xa, order)
50
51 function _max(a,b) return (a+b+abs(a-b))/2 end
52 function _min(a,b) return (a+b-abs(a-b))/2 end
53
54 _Proj(p) = _max( za, _min( zb, -(1/λ)*p ) )
55
56 function a((RuT,RuF),(RvT,RvF))
57     VRu = ∇(RuT) + ∇(RuF)
58     VRv = ∇(RvT) + ∇(RvF)
59     return ∫(VRu · VRv)dΩp
60 end
61
62 # Mixed-order stabilisation
63 hT = CellField(sqrt.(get_cell_measure(Ωp)), Ωp)
64 function ss(u,v)
65     function SFs(u)
66         u_Ω, u_Γ = u
67         return Pfs(u_Ω) - u_Γ
68     end
69     return ∫((1/hT) * (SFs(u)-SFs(v)))dΓp
70 end
71
72 function sa(u,v)
73     function Sfa(u)
74         u_Ω, u_Γ = u
75         return Pfa(u_Ω) - u_Γ
76     end
77
78     return ∫((1/hT) * (Sfa(u)-Sfa(v)))dΓp
79 end
80
81 ls((vΩ,vΓ),pΩ) = ∫(f*vΩ)dΩp + ∫(_Proj(pΩ)*vΩ)dΩp
82 la((vΩ,vΓ),yΓ) = ∫((yΓ-yΩ)*vΩ)dΩp
83
84 function patch_weakform_s(X,Y,pΩ)
85     u, v = get_trial_fe_basis(X), get_fe_basis(Y)
86     Xp = PatchFESpace(X,ptopo)
87     Ru,Rv = Rs(u), Rs(v)
88     dc = DomainContribution()
89     Xp = PatchFESpace(X,ptopo)
90     data = collect_and_merge_cell_matrix_and_vector(
91         assem_s, (X, Y, ss(u,v), ls(v,pΩ), zero(X)),
92         (Xp, Xp, a(Ru,Rv), dc, zero(Xp))
93     )
94     return assemble_matrix_and_vector(assem_s,data)
95 end
96
97 function patch_weakform_a(X,Y,yΩ)
98     u, v = get_trial_fe_basis(X), get_fe_basis(Y)
99     Xp = PatchFESpace(X,ptopo)
100     Ru,Rv = Ra(u), Ra(v)
101     dc = DomainContribution()
102     Xp = PatchFESpace(X,ptopo)
103     data = collect_and_merge_cell_matrix_and_vector(
104         assem_a, (X, Y, sa(u,v), la(v,yΩ), zero(X)),
105         (Xp, Xp, a(Ru,Rv), dc, zero(Xp))
106     )
107     return assemble_matrix_and_vector(assem_a,data)
108 end
109
110 assem_s = PatchAssembler(ptopo,Xs,Ys)
111 assem_a = PatchAssembler(ptopo,Xa,Ya)
112
113 # Initialize and solve KKT
114 ph = FEFunction(Xa[1], zeros(num_free_dofs(Xa[1])))
115 tol = 1e-6, max_iter = 25
116 function solve_KKT(p0,tol,max_iter)
117     iter = 0
118     Er = 1.0
119     yΩ = nothing, pΩ = nothing
120     yΓ = nothing, pΓ = nothing
121     while (Er > tol) && (iter < max_iter)
122         iter += 1
123         op_s = StaticCondensationOperator(
124             Xs,Vs,Ns,assem_s,patch_weakform_s(Xs,Ys,pΩ))
125         yΓ = solve(op_s.sc_op)
126         yΩ = backward_static_condensation(op_s,yΓ)
127         op_a = StaticCondensationOperator(
128             Xa,Ya,Na,assem_a,patch_weakform_a(Xa,Ya,yΩ))
129         pΓ = solve(op_a.sc_op)
130         pΩ = backward_static_condensation(op_a,pΓ)
131         Er = sqrt( sum( ∫( (pΩ - p0)·(pΩ - p0) )dΩp ) )
132         println("iter: $iter, Er: $Er")
133         p0 = pΩ
134     end
135     return yΩ, pΩ, yΓ, pΓ
136 end
137
138 end
139 # optimal state, adjoint and control
140 sol = solve_KKT(ph,tol,max_iter)
141 yΩ, pΩ, yΓ, pΓ = sol;
142 zΩ = _Proj(pΩ)
143
144 ey = yΩ - yex
145 ep = pΩ - pex
146 ez = zex - zΩ
147 el2yΩ = sqrt( sum( ∫(ey * ey)*dΩp ) )
148 el2pΩ = sqrt( sum( ∫(ep * ep)*dΩp ) )
149 el2zΩ = sqrt( sum( ∫(ez * ez)*dΩp ) )
```