

Example: Mixed-order HHO Stokes

```

1 using Gridap
2 using Gridap.Geometry, Gridap.FESpaces
3 using Gridap.CellData, Gridap.Fields
4 using Gridap.ReferenceFES, Gridap.Arrays
5 using Gridap.MultiField
6
7 u(x) = VectorValue(x[1],-x[2])
8 p(x) = x[1] + x[2]
9 f(x) = -Δ(u) - ∇(p)(x)
10
11 model = voronoi_mesh((0,1,0,1),(6,6))
12 Ω = Triangulation(ReferenceFE{2}, model)
13 Γ = Triangulation(ReferenceFE{1}, model)
14
15 order = 1
16 V = FESpaces.PolytopalFESpace(
17   Ω, VectorValue{2,Float64}, order+1
18 )
19 M = FESpaces.PolytopalFESpace(
20   Γ, VectorValue{2,Float64}, order;
21   dirichlet_tags="boundary"
22 )
23 N = TrialFESpace(M,u)
24
25 Q = FESpaces.PolytopalFESpace(Ω, Float64, order)
26 Q̄ = FESpaces.PolytopalFESpace(
27   Ω, Float64, order; local_kernel=:constants
28 )
29 Q̄ = FESpaces.PolytopalFESpace(Ω, Float64, 0)
30 Λ = ConstantFESpace(Ω)
31
32 style = BlockMultiFieldStyle(2,(2,3))
33 X = MultiFieldFESpace([V, Q̄, N, Q̄, Λ];style)
34 Y = MultiFieldFESpace([V, Q̄, M, Q̄, Λ];style)
35
36 ptopo = PatchTopology(model)
37 Qp = PatchTriangulation(model,ptopo)
38 Γp = PatchBoundaryTriangulation(model,ptopo)
39
40 qdegree = 2*(order+1)
41 dΩ = Measure(Ω,qdegree)
42 dQp = Measure(Qp,qdegree)
43 dΓp = Measure(Γp,qdegree)
44
45 YR = MultiFieldFESpace(
46   [V, M];style=BlockMultiFieldStyle(2,(1,1))
47 )
48 function adapt_ids(op)
49   function adapt_ids(u)
50     return MultiFieldFEBasis(
51       op(MultiFieldFEBasis(u,[1,2],2)), [1,3], 5
52     )
53   end
54 end
55
56 d = adapt_ids(
57   divergence_operator(Ω,ptopo,YR,order)
58
59 R = adapt_ids(
60   reconstruction_operator_vec(Ω,ptopo,YR,order)
61 )
62 hT = CellField(sqrt.(get_cell_measure(Qp)), Ωp)
63 PΓ = projection_operator(M, Γp, dΓp)
64
65 function a((Ru_Ω, Ru_Γ),(Rv_Ω, Rv_Γ))
66   VRu = ∇(Ru_Ω) + ∇(Ru_Γ)
67   VRv = ∇(Rv_Ω) + ∇(Rv_Γ)
68   return ∫(VRu ⋅ VRv)dΩp
69 end
70
71 function s(u,v)
72   SΓ((uT, uF)) = PΓ(uT) - uF
73   return ∫((1/hT) * (SΓ(u)⋅SΓ(v)))dΓp
74 end
75
76 b((Du_Ω, Du_Γ),q) = ∫((Du_Ω + Du_Γ)⋅q)dΩp
77 c(q,λ) = ∫(q⋅λ)dΩp
78 l((vΩ,vΓ)) = ∫(f⋅vΩ)dΩp
79
80 function weakform(ptopo,assem,X,Y)
81   Xp = FESpaces.PatchFESpace(X,ptopo)
82   x, y = get_trial_fe_basis(X), get_fe_basis(Y)
83
84   u, p̄, p̄, λ = (x[1],x[3]), x[2], x[4], x[5]
85   v, q̄, q̄, μ = (y[1],y[3]), y[2], y[4], y[5]
86   p, q = p̄ + p̄, q̄ + q̄
87
88   Ru, Rv = R(u), R(v)
89   Du, Dv = D(u), D(v)
90
91   data = collect_and_merge_cell_matrix_and_vector(
92     assem,
93     (Xp, Xp, a(Ru,Rv), DomainContribution(), zero(Xp)),
94     (X, Y, s(u,v)+c(p̄,u)+c(q̄,λ), l(v), zero(X)),
95     (X, Xp, b(Dv,p), DomainContribution(), zero(X)),
96     (Xp, X, b(Du,q), DomainContribution(), zero(Xp))
97   )
98   assemble_matrix_and_vector(assem,data)
99 end
100
101 assem = PatchAssembler(ptopo,X,Y)
102 op = MultiField.StaticCondensationOperator(
103   X,assem,weakform(ptopo,assem,X,Y)
104 )
105
106 xh = solve(op)
107 uT, uF, ph = xh[1], xh[3], xh[2]+xh[4]
108
109 R = reconstruction_operator_vec(Ω,ptopo,YR,order)
110 uh = MultiFieldCellField([uT,uF])
111 Ruh = R(uh)
112
113 l2_err = sqrt(sum([((uh - u)⋅(uh - u))*dΩ]))

```