

Example: Upwinding

```
1 bra_ket(a::CellField) = a.+ - a.- 17
2 bra_ket(a::SkeletonPair{<:CellField}) = a.+ - a.- 18 # Initial condition and velocity field as per
3 19 # SUPG example
4 function upwinding(model,dt,t0,t,tableau,ls,nls) 20
5 # Triangulation, geometrical info 21 # Bilinear forms
6 Ω = Triangulation(model) 22 upwind = 0.5*abs((w·n_Λ).+)
7 Λ = SkeletonTriangulation(model) 23 a(u,v) = ( ∫(-(u*(∇(v)·w))*meas_Ω)dΩ
8 dΩ, dΛ = Measure(Ω,4), Measure(Λ,4) 24 + ∫(0.5*bra_ket((w*u)·n_Λ)*bra_ket(v)*meas_Λ.+)dΛ
9 n_Λ = get_normal_vector(Λ) 25 s(u,v) = ∫(upwind*bra_ket(u)*bra_ket(v)*meas_Λ.+)dΛ
10 meas_Ω = MeasureCellField(Ω) 26
11 meas_Λ = MeasureCellField(Λ) 27 mass(t,dtu,v) = ∫((dtu*v)*meas_Ω)dΩ
12 28 res(t,u,v) = a(u,v) + s(u,v)
13 # Finite element space 29 jac(t,u,du,v) = a(du,v) + s(du,v)
14 reffe = ReferenceFE(lagrangian,Float64,1) 30 jac_t(t,u,dtu,v) = mass(t,dtu,v)
15 Q = TestFESpace(model, reffe; conformity=:L2) 31 # Transient operator and solver as per SUPG example
16 P = TrialFESpace(Q) 32 end
```