

Seismic Solvability Problems

August Lau and Chuan Yin

Email contact: chuan.yin@apachecorp.com

December 6, 2012

Abstract

Classical approach of solvability problem has shed much light on what we can solve and what we cannot solve mathematically. Starting with quadratic equation, we know that we can solve it by the quadratic formula which uses square root. Polynomial is a generalization of quadratic equation. If we define solvability by using only square roots, cube roots etc, then polynomials are not solvable by radicals (square root, cube root etc). We can classify polynomials into simple (solvable by radicals) and complex (not solvable by radicals). We will use the same metaphor to separate what is solvable (simple part) and what is not solvable (complex part).

This paper is a result of our presentation at a University of Houston seminar. In this paper, we will study seismic complexity through the eyes of solvability. We will investigate model complexity, data complexity and operator complexity. Model complexity is demonstrated by multiple scattering in a complex model like Cantor layers. Data complexity is studied through Betti numbers (topology/cohomology). Data can be decomposed as simple part and complex part. The simple part is solvable as an inverse problem. The complex part could be studied qualitatively by topological method like Betti numbers. Operator complexity is viewed through semigroup theory, specifically through idempotents (opposite of group theory). Operators that form a group are invertible (solvable) while semigroup of operators is not invertible (not solvable) in general.

Seismic Solvability Problems

August Lau and Chuan Yin

Invitation by Professor Art Weglein
University of Houston
Feb 28, 2012

Figure 1: Slide 1

Short history of solvability:

<< simplicity >>

Quadratic equation (Complex numbers)

Fundamental theorem of algebra (Gauss)

Solvable by radicals (Abel)

Group theory (Galois/solvable group, Lie/continuous group)

Operator theory (Hilbert, infinite dimensional space)

<< complexity >>

Numerical complexity (Poincare /chaos)

Model complexity (Cantor / layers)

Data complexity (Betti number/ diffractions)

Operator complexity (Idempotent semigroup/ 2-way wave)

Complex Decomposition (Data or operator)

= Simple part (quantitative/solvable)

+ Complex part (qualitative/interpretable/not noise)

Figure 2: Slide 2

Presentation based primarily on 4 papers published on arXiv




Figure 3: Slide 3

Part 1: Model complexity (Cantor / layers): Cantor set models and solvability of multiples

Figure 4: Slide 4

The Cantor Set

Construction: repeatedly removing middle thirds of line segments.

The Cantor set = all points that are not removed at any step in this infinite process.




Figure 5: Slide 5

Example 1 – Discrete Horizontal Cantor Set Model: C4




Figure 6: Slide 6

C is sparse and totally disconnected
 $C+C=I$ is dense and nowhere disconnected

Multiples may not be solvable for a Cantor set medium

The Cantor Set Models: No Means + No Variance
 (No Effective Medium)

Figure 7: Slide 7

Example 2 – Discrete Vertical Cantor Set Model: VC6




Figure 8: Slide 8

Example 2 – Discrete Vertical Cantor Set Model: VC6




Figure 9: Slide 9

Near and Far Stacks See Different Models of Complex Topology




Figure 10: Slide 10

Example 3 - Sierpinski Carpet: a 2-D Generalization of the Cantor Set

Construction: divide a square into 9 equal sub-squares in a 3-by-3 grid, and remove the center sub-square; repeat the process for the remaining 8 sub-squares; and apply the process recursively.




Figure 11: Slide 11

Example 3 – Discrete Sierpinski Carpet Model: SP4




Figure 12: Slide 12

Example 3 – Discrete Sierpinski Carpet Model: SP4





Figure 13: Slide 13

Example 3 - Complex topology in the overburden



Results are generated from a deterministic model without adding “random noise”

Figure 14: Slide 14

Example 3 – Sierpinski Carpet Models: SP4




Figure 15: Slide 15

Model complexity Summary

- The Cantor set:
 - The Cantor set C is sparse and totally disconnected; while $C+C=I$ is a continuum that is dense and nowhere disconnected
 - The Sierpinski Carpet is a 2-D generalization of the Cantor set.
- Example 1 (horizontal Cantor set models):
 - Multiples are not solvable for the Cantor set model
 - No means + no variance (no effective medium)
- Example 2 (vertical Cantor set models):
 - “Noise” from inversion might be an indication on the earth’s complex topology
- Example 3 (Sierpinski Carpet models):
 - A model with complex topology can generate realistically looking, complex wave field

Figure 16: Slide 16

**Part 2: Data complexity (Betti number/
diffractions):
Geometric simplicity as a migration criterion**

Figure 17: Slide 17

Betti numbers and homology groups

- Homology is a tool to measure connectivity and holes in a topological space; Betti numbers are dimensions of homological groups.
- The n th Betti number, B_n , represent “ n -dimensional holes”
- For a 2D image, only B_0 and B_1 are non-trivial, $B_n=0$ ($n>1$)
- The 0th Betti number, B_0 , counts the number of connected components
- The 1st Betti number, B_1 , counts the number of “holes”
- The following 3 images are equivalent homologically, i.e. 1 connected component and 1 hole in each




Figure 18: Slide 18

B0 & B1: more examples




Figure 19: Slide 19

Betti numbers and the Computational Homology Project (CHOMP)

- CHOMP is a US-based, international open-source development project for promoting the application of computational topology to global analysis of nonlinear spaces and functions.
- Web address
 - <http://chomp.rutgers.edu/>
- We take advantage of the latest developments in CHOMP to carry out efficient computation of Betti numbers on seismic data

Figure 20: Slide 20

Betti numbers, geometric complexity and wave propagation




Figure 21: Slide 21




Figure 2: A synthetic dataset containing three diffractors.

Figure 22: Slide 22




Figure 3: Zoom-in view on the semigroup migration.

Figure 23: Slide 23




Figure 4: Betti number B1 as a function of migration velocities for the synthetic dataset in Figures 2 and 3.

Figure 24: Slide 24




Figure 5: A 2D stack section before migration.

Figure 25: Slide 25




Figure 6: Zoom-in view on a portion of the dataset from the semigroup migration.

Figure 26: Slide 26





Figure 7: Betti number B1 versus migration velocity, corresponding to Figure 6, that reaches minimum at a migration velocity of around 1800 m/s.

Figure 27: Slide 27

Examples of migration-operator related “noise”



Primaries interfered by numerical artifacts

Figure 28: Slide 28

Proposed steps for reducing migration noise

- Forward model or de-migrate
- Apply desired process, e.g., mixing, to attenuate noise, with one parameter
- Compute Betti numbers on time slices to infer level of geometric complexity
- Analyze Betti numbers and determine optimal processing parameter
- Inverse model or re-migrate

Figure 29: Slide 29

Example 1: scatterers




Figure 2. Input scatterers form a disordered system (it is not coherent and not random)

Figure 30: Slide 30

Example 1: forward model or de-migration




Figure 3a. Diffraction pattern from the scatterers




Figure 3b. Timeslice of diffraction pattern

Figure 31: Slide 31

Example 1: migration with 3% error we desire to re-focus to minimize the migration “smiles”




Figure 4. Migration output with 3% velocity error

Figure 32: Slide 32

Example 1: compute Betti numbers for a varying processing parameter (mixing radius in this example)




Figure 5a. Diffraction pattern after 7x7 mix




Figure 5b. Timeslice of diffraction pattern after 7x7 mix

Figure 33: Slide 33

Example 1: reducing geometric complexity defined by B1




Figure 6. X-axis is amount of mixing and y-axis is Betti numbers




Figure 3b. Timeslice of diffraction pattern



Less complex




Figure 5b. Timeslice of diffraction pattern after 7x7 mix

Figure 34: Slide 34

Example 1: re-migrated with geometric simplicity




Figure 4. Migration output with 3% velocity error





Figure 7. Migrated output after 7x7 mix

Figure 35: Slide 35

Example 2: real data



Primaries interfered by numerical artifacts

Figure 36: Slide 36

Example 2: reducing geometric complexity defined by B1




Figure 37: Slide 37

Example 2: re-migrated with geometric simplicity




Figure 38: Slide 38

Geometric simplicity and seismic imaging

- Geometric simplicity as defined by the Betti numbers can be used for quantitatively determining impact of processing parameters
- Seismic imaging should always start from simple geometry of the input data to build intuition for the migration operator
- As we build better understanding of the data and the operator, we can increase the Betti numbers and increase the geometric complexity for migration

Figure 39: Slide 39

Summary

- Geometric simplicity can be defined by Betti numbers
- CHOMP made it possible for efficient computation of Betti numbers
- Examples demonstrated usage of Betti numbers for reducing migration artifacts
- This approach can be easily generalized to other applications, such as tomography and waveform inversion

Figure 40: Slide 40

Part 3: Operator complexity (idempotent semigroup) :

2-way wave field extrapolation and imaging

Figure 41: Slide 41

Complex decomposition of operators: An example of wave field extrapolation of 1D acoustic wave equation

$$\frac{d}{dz} \begin{bmatrix} \hat{p} \\ \frac{1}{\rho} \frac{d\hat{p}}{dz} \end{bmatrix} = \begin{bmatrix} 0 & \rho \\ -\frac{\omega^2}{\rho c^2} & 0 \end{bmatrix} \begin{bmatrix} \hat{p} \\ \frac{1}{\rho} \frac{d\hat{p}}{dz} \end{bmatrix} \implies \frac{d}{dz} \mathbf{f} = \mathbb{A} \mathbf{f} \implies \mathbf{f} = e^{z\mathbb{A}} \mathbf{f}_0$$

Diagonalize: Another way of further analyzing Eq.(4) is to examine eigenvalues and eigenvectors of $\mathbb{A}$, i.e., $\mathbb{A} = \mathbb{V}\mathbb{D}\mathbb{V}^{-1}$, where $\mathbb{V}$ is the eigenvector matrix, $\mathbb{D}$ diagonal matrix of the eigenvalues.

Eq.(4) becomes

$$\mathbf{f} = \mathbb{V} e^{z\mathbb{D}} \mathbb{V}^{-1} \mathbf{f}_0, \quad (6)$$

where the diagonal eigenvalue matrix is

$$\mathbb{D} = \begin{bmatrix} -i\frac{\omega}{c} & 0 \\ 0 & i\frac{\omega}{c} \end{bmatrix}, \quad (7)$$

Apply projection: $\mathbf{g} = \mathbb{V}^{-1} \mathbf{f} \implies \mathbf{g} = e^{z\mathbb{D}} \mathbf{g}_0$

Operator: $\mathbb{L} = e^{z\mathbb{D}} = \mathbb{P}_1 + \mathbb{P}_2 = \mathbf{e}_1 e^{z\mathbb{D}} + \mathbf{e}_2 e^{z\mathbb{D}}$

where

$$\mathbf{e}_1 = \begin{bmatrix} 1 & 0 \\ 0 & 0 \end{bmatrix} \text{ and } \mathbf{e}_2 = \begin{bmatrix} 0 & 0 \\ 0 & 1 \end{bmatrix} \text{ are idempotents which correspond to upward-propagating and downward-propagating components of the wavefield, respectively.}$$

Figure 42: Slide 42

Complex decomposition of operators: Methodology

We will first introduce some mathematical concepts in semigroup and group theory. In order to make it less abstract, we will think of operators as matrices since matrices are a good surrogate to discuss abstract ideas. If we take all $n \times n$ matrices under matrix multiplication as a whole system, it is a semigroup and it has the semigroup property of associative law $A(BC) = (AB)C$. This system includes both invertible and noninvertible matrices. We will come back to the idea of semigroup and idempotents in semigroups.

If we restrict a subset to all invertible matrices, then it is a group since each $n \times n$ invertible matrix A by definition will have a B so that $AB = BA = I$ the identity matrix. Two matrices are equivalent if $A = UB$ where U and V are invertible. A desirable property is to write a matrix as $A = UDV$ where D is a diagonal matrix. More generally, it is desirable to have $A = UPV$ where P is an idempotent with $PP = P$.

Figure 43: Slide 43




Figure 1: A lower energy, stable state can be reached by multiplication of idempotents.

Figure 44: Slide 44

Complex decomposition of operators

Decomposition of operators (with predetermined basis)

The simplest way to decompose an operator is to use a predetermined basis like Fourier basis. The advantage of predetermined basis is to convert a differential equation into an algebraic equation with orthogonal basis like fk (f is frequency and k is wavenumber). The evanescent wave is just filtering certain dips (i.e. certain fk numbers)(Figure 2). The disadvantage is the difficulty of handling large velocity variations.

Any predetermined basis forces an operator decomposition into predetermined geometry like Fourier basis. The predetermined basis maps the operators into fixed shapes given by the basis elements.

Decomposition of operators (without predetermined basis)

The second method is to lump the derivatives with the velocity field so it is more sensitive to the velocity variations. Finite difference and Kirchhoff extrapolation are such methods but they can have practical limitations for frequencies and dips. Integral methods like Kirchhoff extrapolation (see Berryhill) are more geometrically motivated. An excellent numerical treatment can be found in Sandberg and Beylkin 2009 where positive eigenvalues are viewed as evanescent energy. The negative and zero eigenvalues are kept as propagating waves in the extrapolation operator. This is another way to separate the wavefield into simple part and complex part.

Figure 45: Slide 45

Complex decomposition of operators

Conclusion

Solvability by semigroup is a way to use noninvertible operators to approximate the original operator. We have chosen in this paper to use idempotents P where $PP = P$. Semigroup theory is not restricted to idempotents but idempotents are easier to demonstrate since they resemble diagonal matrices (see Davies, Wilansky). They are also familiar to physicists in terms of density matrix with 0 or 1 eigenvalues (see Bowler et al) viewed as basic building blocks.

Multiplication of noninvertible operators becomes less energetic or contractive or lossy or more limited. Addition of noninvertible operators becomes more energetic or expansive or generating larger operator. Toggling between multiplication and addition of the idempotents gives us the stable part (multiplicative) and the generative part (addition). This is the essence of downward continuation in wavefield extrapolation. The schematic is captured with the diagram in the end (Figure 1).

The simple part of the wavefield extrapolation operator is written as the sum of idempotent operators ($A = P_1 + P_2 + P_3 + \dots$) where A is the operator and P_j is an idempotent with $P_j P_j = P_j$ and $P_j P_k = 0$ if P_j and P_k are different. We dropped the phrase equivalent to idempotent to emphasize the importance of idempotents. The simple part of the operator is the propagating operator to extrapolate the wavefield. It can be studied through semigroup of operators. The complex part of the operator is the evanescent energy which should not be propagated. The complex part needs qualitative mathematics like topology to classify and understand.

Figure 46: Slide 46

Short history of solvability:

<< simplicity >>

Quadratic equation (Complex numbers)

Fundamental theorem of algebra (Gauss)

Solvable by radicals (Abel)

Group theory (Galois/solvable group, Lie/continuous group)

Operator theory (Hilbert, infinite dimensional space)

<< complexity >>

Numerical complexity (Poincare /chaos)

Model complexity (Cantor / layers)

Data complexity (Betti number/ diffractions)

Operator complexity (Idempotent semigroup/ 2-way wave)

Complex Decomposition (data is operator and operator is data)

= Simple part (solvable) + Complex part (interpretable)

Toy Modeling : Simple + Simple = Complex (C+C=I with Cantor + Cantor = Continuum)

Complex Decomp of data : Complex = Simple + Complex (low Betti + high Betti)

Complex Decomp of operator : Simple + Simple = Complex (low rank + low rank = high rank)

Figure 47: Slide 47