

The manual for the numerical integrator for the Thermodynamic Quantum Fokker–Planck Equation (T-QFPE)

The numerical integrator for the Thermodynamic Quantum Fokker–Planck Equation (T-QFPE) consists of the following source files.

- MAIN.cpp
- MAIN.h
- LTFP.cpp
- LTFP.h
- CUDA_LTFP.cu
- CUDA_LTFP.cuh
- HEOMToolkit.cpp
- HEOMToolkit.h

The “MAIN.cpp” and “MAIN.h” files contain the demonstration code. The Open Multi-Processing (OMP) program is presented in the files “LTFP.cpp” and “LTFP.h”, and the Compute Unified Device Architecture (CUDA) program is presented in the files “LTFP_CUDA.cpp” and “LTFP_CUDA.h”.

We provide the following four demonstration functions:

- EquilibriumDistribution
- LinearResponseFunction
- CorrelationFunction
- QuantumStirling

Here, “EquilibriumDistribution”, “LinearResponseFunction”, “CorrelationFunction”, and “QuantumStirling” are the functions for calculating the equilibrium Wigner distribution function, the linear response function, the correlation function and the dynamics of the Quantum Stirling Engine (QSE). To use them, specify the name of the function in the “main” program. For example, to run the “EquilibriumDistribution” function, specify as follows,

```
int main()
{

    LogFile.open("log.txt", std::ios::out);

#ifdef UseCUDA
    LogFile << "This is CUDA mode.\n" << endl;
#else
    LogFile << "This is CPU mode.\n" << endl;
#endif

    EquilibriumDistribution();

    LogFile.close();

    return 0;
}
```

The system Hamiltonian

In this numerical integrator, we defined the system Hamiltonian as follows,

$$\hat{H}_A(t) = \frac{\hat{p}^2}{2m} + U(\hat{q}; t), \quad (1)$$

where $U(\hat{q}; t)$ is the time-dependent potential expressed as

$$U(\hat{q}; t) = -E(t)\hat{q} + U_2\hat{q}^2 + U_3\hat{q}^3 + U_4\hat{q}^4. \quad (2)$$

Here, $E(t)$ is the external field (e.g. the electric field), and U_2, U_3 and U_4 are the time-independent Taylor coefficients.

Parameters of the T-QFPE

The parameters in the TFP and LTFP CUDA classes are defined as

- N : the depth of the hierarchy ($N \geq 1$)
- K : the number of the Pade frequencies ($1 \leq K \leq 5$)
- MeshQ : the size of the mesh in the position direction
- MeshP : the size of the mesh in the momentum direction
- dq : the position step in the mesh
- dp : the momentum step in the mesh
- DimU : the dimension of the potential ($1 \leq \text{DimU} \leq 4$)
- dt : the time step
- m : the mass of the particle

Note that MeshQ and MeshP must be a multiple of 16 in order for the CUDA program to be used.

Setting the time-dependent parameters

The LTFP and LTFP_CUDA classes have the three time-dependent parameters, A , T , and PotenC , where A is the system-bath coupling strength, T is the bath temperature, and PotenC is the Taylor coefficients of the potential surface. These variables are arrays because when we perform the one step time evolution from time t to $t + dt$ using the 4th order Runge-Kutta method, we need the values of the time-dependent parameters at the three times t , $t + dt/2$, and $t + dt$. Then, we input the time-dependent parameters at the time t , $t + dt/2$ and $t + dt$ in the 0th, 1st, and 2nd elements of the arrays A , T , and PotenC , respectively. The n th element of the $\text{PotenC}[i]$ ($i = 0, 1, 2$) is the $(n + 1)$ th order of the Taylor coefficient of the potential surface. For example, if the time dependent-parameters satisfy the following equations

$$A(t) = 1.0, \quad T(t) = 1.0, \quad U(q, t) = 0.5q^2 + 0.3q,$$

$$A(t + dt/2) = 0.9, \quad T(t + dt/2) = 1.1, \quad U(q, t) = 0.5q^2 + 0.4q,$$

and

$$A(t + dt) = 0.8, \quad T(t + dt) = 1.2, \quad U(q, t) = 0.5q^2 + 0.5q,$$

the code should be written as follows,

```

// Parameters at time t
A[0] = 1.0;
T[0] = 1.0;
U[0][0] = 0.3;
U[0][1] = 0.5;

// Parameters at time t + dt / 2
A[1] = 0.9;
T[1] = 1.1;
U[1][0] = 0.4;
U[1][1] = 0.5;

// Parameters at time t + dt
A[2] = 0.8;
T[2] = 1.2;
U[2][0] = 0.5;
U[2][1] = 0.5;

```

In the “QuantumStirling” function, the time-dependent parameters are set in the “SetParameters” function as follows.

```

void SetParameters()
{
    double BufTime;

    for (int abon = 0; abon <= 2; ++abon) {

        BufTime = NowTime + (double)(abon) * H.dt * 0.5;

        SetPotential(BufTime, H.PotenC[abon]);
        H.A[abon] = FuncA(BufTime);
        H.T[abon] = FuncT(BufTime);

    }

}

```

This function set the time-dependent variables A, T, and PotenC using the “SetPotential”, “FuncA”, and “FuncT” functions corresponding to $U(q, t)$, $A(t)$, and $T(t)$, respectively. Changing these functions is therefore only necessary to set the time-dependent parameters.

Performing the one-step time evolution

We provided the two numerical integration programs using the 4th order Runge–Kutta method and the predictor–corrector method.

One step time evolution with the 4th order Runge–Kutta

To use the predictor–corrector method, first set the parameters of the T-QFPE and call “Setup_RK4” function as follows.

```
// Input Fundamental Parameters
////////////////////////////////////

H.N = 7; // the depth of the hierarchy
H.K = 2; // the number of Pade frequencies

// the distance between the neighbor discretized points
H.dq = 0.3; // position
H.dp = 0.5; // momentum

// the mesh size of the position and the momentum

H.MeshQ = 64; // position
H.MeshP = 64; // momentum

// the dimension of the subsystem potential
H.DimU = 4;

// time per step
H.dt = 0.001;

H.Setup_RK4();
H.ResetWigner(1.0, 1.0);
```

Here, “H.ResetWigner(double Alpha, double Beta)” is the function for set the initial Winger distribution function expressed as,

$$W(p, q) = \frac{\beta}{2\pi} \sqrt{\frac{\alpha}{m}} \exp \left[-\beta \left(\frac{p^2}{2m} + \frac{1}{2} \alpha q^2 \right) \right], \quad (3)$$

where $\alpha = \text{Alpha}$, $\beta = \text{Beta}$, and m is the mass of the particle.

After completing the setup procedure, one-step time evolution can be performed by calling the LTFP function (CUDA.LTFP) “H.OneStepEvolution_RK4”. For example,

we can perform 10000 steps of time evolution, then output the step number and the expectation values evaluated as $\hat{q}^2$ and $\hat{p}^2$ in the “Data.csv” in the csv format as follows,

```
std::ofstream DataFileStream;

DataFileStream.open(''Data.csv'', std::ios::out);

for (int tbon = 1; tbon <= maxcount; ++tbon) {

    H.OneStepEvolution_RK4();

    // output
    DataFileStream << setprecision(18) << '','' << tbon
        << '','' << H.GetExpQ2() << '','' << H.GetExpP2()
        << std::endl;

}
```

Here, the member functions “H.GetExpQ2” and “H.GetExpP2” are the functions for outputting the expectation value of $\hat{q}^2$ and $\hat{p}^2$, respectively. The other functions for calculating physical variables are summarized in the later section “The functions for output”.

One-step time evolution with the predictor-corrector method

To use the predictor-corrector method, first set the T-QFPE parameters, then call “Setup_PCM” function as follows.

```

// Input Fundamental Parameters
////////////////////////////////////

H.N = 7; // the depth of the hierarchy
H.K = 2; // the number of Pade frequencies

// the distance between the neighbor discretized points
H.dq = 0.3; // position
H.dp = 0.5; // momentum

// the mesh size of the position and the momentum

H.MeshQ = 64; // position
H.MeshP = 64; // momentum

// the dimension of the subsystem potential
H.DimU = 4;

// time per step
H.dt = 0.001;

H.Setup_PCM();
H.ResetWigner(1.0, 1.0);
H.ResetPCCounter();

```

Because the predictor-corrector method utilizes the Wigner auxiliary functions in the previous 3 steps, the program performs the one-step time evolution using the 4th order Runge-Kutta method for the 3 steps. To count these 3 steps, the LTFP(LTFP_CUDA) class has a member variable “PCCounter”. We can reset “PCCounter” using the member function “ResetPCCounter” of LTFP(LTFP_CUDA). Note that because the predictor-corrector method is based on the extrapolation, it is recommended to call the “ResetPCCounter” function whenever the thermodynamic process changes, for example, changes from the isothermal process to the thermostatic process.

After completing the setup procedure, a one-step time evolution can be run each time by calling the member function of the LTFP (CUDA_LTFP) “H.OneStepEvolution_RK4”. The following sample code performs a 10000-step time evolution and outputs the step number and the expectation values of $\hat{q}^2$ and $\hat{p}^2$ to the “Data.csv” file in csv format.

```

std::ofstream DataFileStream;

DataFileStream.open(''Data.csv'', std::ios::out);

for (int tbon = 1; tbon <= maxcount; ++tbon) {

    H.OneStepEvolution_PCM();

    // output
    DataFileStream << setprecision(18) << '','' << tbon
        << '','' << H.GetExpQ2() << '','' << H.GetExpP2()
        << std::endl;

}

```

The functions for output

The LTFP (CUDA_LTFP) class has the following functions for output.

GetNorm()

This function outputs the norm of the Wigner distribution function, $\langle 1 \rangle$. Here, the bracket $\langle \bullet \rangle$ is defined as

$$\langle f(p, q) \rangle = \int_{q_{\min}}^{q_{\max}} dq \int_{p_{\min}}^{p_{\max}} dp f(p, q) W_{\vec{0}}(p, q; t), \quad (4)$$

for an arbitrary function $f(p, q)$, where $q_{\min}$, $q_{\max}$, $p_{\min}$, and $p_{\max}$ are the minimum and maximum of the domains of the position and the momentum, respectively.

GetExpQ()

These function show the expectation value of $\hat{q}$, $\langle q \rangle$.

GetExpQ2()

These function show the expectation value of $\hat{q}^2$, $\langle q^2 \rangle$.

GetExpQ3()

These function show the expectation value of $\hat{q}^3$, $\langle q^3 \rangle$.

GetExpQ4()

These function show the expectation value of $\hat{q}^4$, $\langle q^4 \rangle$.

GetExpP2()

These function show the expectation value of $\hat{p}^2$, $\langle p^2 \rangle$.

GetWDF(std::ofstream& DistributionFile)

This function outputs the Winger distribution function (WDF) $W_{\bar{0}}(q, p; t)$ in the csv file format, $q, p, W_{\bar{0}}(q, p; t)$.

GetPositionDistribution(std::ofstream& DistributionFile)

This function outputs the position distribution function $P(q; t)$ in the csv file format, $q, P(q; t)$. The position distribution function, $P(q; t)$, is defined as

$$P(q; t) = \int_{p_{\min}}^{p_{\max}} W_{\bar{0}}(q, p; t) dp. \quad (5)$$

GetInternalEnergy()

This function outputs the internal energy defined as

$$U(t) = \int_{q_{\min}}^{q_{\max}} dq \int_{p_{\min}}^{p_{\max}} dp \left[\left\{ \frac{p^2}{2m} + (U_2 q^2 + U_3 q^3 + U_4 q^4) \right\} W_{\bar{0}}(p, q; t) \right]. \quad (6)$$

GetWint()

This function outputs the intensive work defined as

$$\frac{dW^{int}(t)}{dt} = -\langle q \rangle \frac{dE(t)}{dt}. \quad (7)$$

GetWext()

This function outputs the extensive work defined as

$$\frac{dW^{ext}(t)}{dt} = E(t) \frac{d\langle q \rangle}{dt}. \quad (8)$$

GetQ()

This function outputs the heat defined as

$$\frac{dQ_A(t)}{dt} = \int_{q_{\min}}^{q_{\max}} dq \int_{p_{\min}}^{p_{\max}} dp \left\{ \left(\frac{p^2}{2m} + U(q; t) \right) \frac{\partial W_{\bar{0}}(q, p; t)}{\partial t} \right\}. \quad (9)$$

GetDLWint()

This function outputs the dimensionless intensive work defined as

$$\frac{d\tilde{W}^{int}(t)}{dt} = U(t) \frac{d\beta(t)}{dt} - \langle q \rangle \frac{d\tilde{E}(t)}{dt}, \quad (10)$$

where $\beta(t) = 1/k_B T(t)$ is the inverse temperature of the bath, and $\tilde{E}(t) = \beta(t) E(t)$.

GetDLWext()

This function outputs the dimensionless extensive work defined as

$$\frac{d\tilde{W}^{ext}(t)}{dt} = U(t) \frac{d\beta(t)}{dt} + \tilde{E}(t) \frac{d\langle q \rangle}{dt}. \quad (11)$$

GetDLQext()

This function outputs the dimensionless extensive heat defined as

$$\frac{d\tilde{Q}^{ext}(t)}{dt} = \beta(t) \frac{dU(t)}{dt} - \tilde{E}(t) \frac{d\langle q \rangle}{dt}. \quad (12)$$

Functions for acting operators to the auxiliary Wigner distribution functions

The member functions of the LTFP(CUDA_LTFP) class, which act as operators on the auxiliary Wigner distribution functions (WDFs), are described here. These functions are used in the “LinearResponseFunction” and “CorrelationFunction” demonstration codes.

MultiplyQ()

This function multiplies q to the auxiliary WDFs $W_{\vec{n}}(p, q; t)$.

DifferentiateWithP

This function differentiate the auxiliary WDFs $W_{\vec{n}}(p, q; t)$ with p .

Functions for freeing the allocated memory

Before finishing the LTFP(LTFP_CUDA) class object, the CPU memory must be cleaned. For the 4th Runge-Kutta method, call the member function “Free_RK4”, while for the Predictor-Corrector method, call the member function “Free_PCM”.

Compiling the program

for Windows machines

In the MS Windows environment, compile the program using Visual Studio 2022, which can be downloaded from the following Web site.

<https://visualstudio.microsoft.com/vs/>

To use the OMP program, the following procedure is necessary

1. Right click “LTFP” in the Solution Explorer, and select “properties”.

2. Select “Language” in the “C/C++” tab.
3. Input “Yes(/openmp)” in the “Open MP Support” box.

Then, compile the program by clicking “Build Solution” in the “Build” tab on the top of the window. The exe file will be created in the “LTFP\x64” directory.

To use the CUDA program, the “CUDA Toolkit” has to be installed on your computer. The “CUDA Toolkit” installer is available from the following web site.

<https://developer.nvidia.com/cuda-toolkit>

Then perform the following steps.

1. Right-click “LTFP” in the Solution Explorer, and select “Build Customizations...” from “Build Dependencies”. Then, check “CUDA ***(.targets, .props)” (***) is the version number of the “CUDA Toolkit”), and click OK button.
2. Right-click “LTFP” in the Solution Explorer, and select “properties”. Select “Input” from the “Linker” tab. Enter “cudart.lib” in the “Additional Dependencies” box and click OK.

You also have to write `#define UseCUDA` on the top of “MAIN.h” file, before you compile the files.

for Linux machine users

To compile under Linux environment, first extract the following 8 files from “LTFP.zip”.

- MAIN.cpp
- MAIN.h
- LTFP.cpp
- LTFP.h
- CUDA_LTFP.cu
- CUDA_LTFP.cuh
- HEOMToolkit.cpp
- HEOMToolkit.h

and put these files in the same directory. Before compiling the program, write

```
#define LinuxMode
```

at the top of the “MAIN.h” file.

To compile the OMP program, use “g++ compiler” and type the following command in the terminal.

```
g++ MAIN.cpp LTFP.cpp HEOMToolkit.cpp -fopenmp
```

Then, the compiled file “a.out” is created in the same directory.

Before compiling the CUDA code, write `#define UseCUDA` at the top of the “MAIN.h” file. Then use the “nvcc compiler” and type the following command in the terminal.

```
nvcc MAIN.cpp CUDA_LTFP.cu HEOMToolkit.cpp
```

The compiled file “a.out” will be created in the same directory.

Running the program

For Windows machine users

For the OMP program, the number of threads is specified by typing

```
$env:OMP_NUM_THREADS=*
```

in the Windows terminal before running the executable. Where * is the number of threads to use.

Then run the program by typing “.\” and the exe file name in the terminal (or Windows power shell). e.g., to run “a.exe”, type as follows.

```
.\a.exe
```

We have tested the program ender in the following environment.

Operating System Windows 11 Pro for Workstations

CPU 13th Gen Intel(R) Core(TM) i9-13900KF 3.00 GHz

Memory 64.0 GB

GPU NVIDIA GeForce RTX 4090

For Linux machine users

To compile the OMP program, select the number of threads by typing

```
export OMP_NUM_THREAD=*
```

in the Linux terminal before executing the compiled file. Where * is the number of threads to use.

You can run the program by typing “./” and the compiled file name in the terminal.
e.g. to run “a.out”, type as follows,

```
./a.out
```

We have tested the program ender in the following environment.

Operating System Almalinux 8.3

CPU Intel(R) Xeon(R) Gold 6212U CPU 2.40 GHz

Memory 192 GB

GPU NVIDIA A100