

```

1. static void switchtec_ntb_remove(struct device *dev)
2. {
3.     struct switchtec_dev *stdev = to_stdev(dev);
4.     struct switchtec_ntb *sndev = stdev->sndev;
5.
6.     if (!sndev)
7.         return;
8.
9.     stdev->link_notifier = NULL;
10.    stdev->sndev = NULL;
11.    ntb_unregister_device(&sndev->ntb);
12.    switchtec_ntb_deinit_db_msg_irq(sndev);
13.    switchtec_ntb_deinit_shared_mw(sndev);
14.    switchtec_ntb_deinit_crosslink(sndev);
15.    kfree(sndev);
16.    dev_info(dev, "ntb device unregistered\n");
17. }

```

```

1. static int switchtec_ntb_init_sndev(struct
    switchtec_ntb *sndev)
2. {
...
7.    sndev->ntb.pdev = sndev->stdev->pdev;
8.    sndev->ntb.topo = NTB_TOPO_SWITCH;
9.    sndev->ntb.ops = &switchtec_ntb_ops;
10.
11.    INIT_WORK(&sndev->check_link_status_work,
        check_link_status_work);
...

```

```

1. static int switchtec_ntb_add(struct device *dev)
2. {
...
7.    stdev->sndev = NULL;
...
16.    sndev->stdev = stdev;
17.    rc = switchtec_ntb_init_sndev(sndev);
18.    if (rc)
19.        goto free_and_exit;
...
49.    rc = ntb_register_device(&sndev->ntb);
50.    if (rc)
51.        goto deinit_and_exit;
52.    stdev->sndev = sndev;
53.    stdev->link_notifier = switchtec_ntb_link_notification;
54.    dev_info(dev, "NTB device registered\n");
...}

```

```

1. static void switchtec_ntb_link_notification(struct
    switchtec_dev *stdev)
2. {
3.     struct switchtec_ntb *sndev = stdev->sndev;
4.
5.     switchtec_ntb_check_link(sndev, MSG_CHECK_LINK);
6. }

```

```

1. static void switchtec_ntb_check_link(struct switchtec_ntb *sndev,
2.     enum switchtec_msg msg)
3. {
...
7.    schedule_work(&sndev->check_link_status_work);
8. }

```